

Partner: Clearone
Model: XAP
Device Type: Volume Mixer

GENERAL INFORMATION

SIMPLWINDOWS NAME:	CMS Clearone XAP Generic Macro
CATEGORY:	Volume
VERSION:	1.0
SUMMARY:	Send generic macros
GENERAL NOTES:	<p>This module is designed to send generic macros not covered by 'CMS Clearone XAP Volume and Mute v1.1.umc'.</p> <p>Device types are available via drop-down selection box in parameter fields labeled 'Device_Type'. Available selections are:</p> <p>AP400 / AP800 / PSR1212 / XAP400 / XAP800</p> <p>Also includes ability to offset macro values easily by using an Analog Initialize. By default, a offset value of 0d would be sent and all macro numbers will reside in a set range of 0 - 50. This allows for easy manipulation when a second range of macro numbers is needed for divisible room scenarios. If a value of 50d is sent, the new range of macro numbers is now 51 - 100.</p>
CRESTRON HARDWARE REQUIRED:	C2-COM, ST-COM
SETUP OF CRESTRON HARDWARE:	RS232 Baud: 38400 Parity: None Data Bits: 8 Stop Bits: 1 Handshaking: RTS/CTS
VENDOR FIRMWARE:	
VENDOR SETUP:	
CABLE DIAGRAM:	CNSP-xxx

Partner: Clearone**Model: XAP****Device Type: Volume Mixer****CONTROL:**

Macro_Offset_Value	A	Analog value generating offset value used for macro numbers being sent. Analog Initialize symbol should be used to set a default value of 0d.
Macro-X-Trig	D	Sends macro number defined in 'Macro-Num-X' parameter field (1-10 available)

FEEDBACK:

Vortex-TX\$	S	Serial signal to be routed to a 2-way RS232 port
--------------------	---	--

PARAMETERS:

Device_Type	P	Specifies device type being controlled for macro (drop-down list)
Device-ID	P	Single numeric value indicating device ID being controlled. For example, a numeric value of '0' would be used for controlling device ID-0.

TESTING:

OPS USED FOR TESTING:	V3.137 (Release)
SIMPL WINDOWS USED FOR TESTING:	SimpleWindows Version 2.07.32
CRES DB USED FOR TESTING:	18.15
SYMBOL LIBRARY USED FOR TESTING:	387
SAMPLE PROGRAM:	CMS Clearone XAP Volume Demo.smw
REVISION HISTORY:	V. 1.0